

# CloudMonitor

FAQ

# FAQ

## Technology Sharing

## Agent installation

## Product usage

## How to Receive Notification from DingDing

CloudMonitor provides an alert notification receiving function for DingTalk groups. You can set up the function for the DingTalk group as follows.


For existing alert policies created for a DingTalk group, you just need to add the callback address of the DingTalk robot to a contact to receive the alerts of the group, without modifying the policies.

### 1. Create a DingTalk robot

#### Create a robot for Dingtalk for PC

On a PC, open the DingTalk group from which you want to receive the alert notifications.

Click the **DingTalk robot** at the top right corner to go to the DingTalk robot setting page.



Click **Custom the Robot** to create a DingTalk robot that can receive alert notifications.



机器人管理





Enter "CloudMonitor alert Notification" in the robot name field, and click **Add and**



Copy the Webhook address.

添加机器人

  
编辑头像

机器人名字:

云监控报警通知

接收群组:

阿里云监控

webhook地址:

https://oapi.dingtalk.com/robot/send?access\_token=c31f

复制

[设置说明](#)

完成

去设置

## 2. Add a DingTalk robot to a contact

Add the Webhook address of the DingTalk robot created in Step 1 to a contact. The alert policy of the contact group to which the contact belongs can receive alert notifications from the DingTalk group.

Log on to the CloudMonitor console, and go to the Contact Page.

Alarm contact management

Alarm Contact

Alarm contact group

All

Please input to query the contact name, phone number, email or

Search

Refresh

New Contact

<input type="checkbox"/>	Name	Phone	Email	All WangWang	Ding robot	Alarm group in	Actions
<input type="checkbox"/>	黄峰	13912345678				test	<a href="#">Edit</a>   <a href="#">Delete</a>

Click **Edit** to add the callback address of the DingTalk robot to an existing contact, or click **Create a Contact** to create a contact that includes a DingTalk robot.

Set alarm contact

---

Name:	<input type="text"/>	
	Contact name should start with a Chinese or English character, and have a length of 2-40 characters consisting of Chinese characters, English letters, numbers, "." and underlines	
Phone:	<input type="text"/>	<input type="button" value="Send verification code"/>
Verification code:	<input type="text"/>	
	Fill in the phone verification code	
Email:	<input type="text"/>	<input type="button" value="Send verification code"/>
Verification code:	<input type="text"/>	
	Fill in the E-mail verification code	
Ali WangWang:	<input type="text"/>	
Ding robot:	<input type="text"/>	
	<a href="#">How to get the Ding robot address</a>	

After the DingTalk robot is added to an existing contact, all alert notifications the contact previously receives via emails and SMSs can now be received through the DingTalk group.