

ApsaraDB for Redis


Quick Start

Quick Start

Quick start flowchart

If you use ApsaraDB for Redis for the first time, refer to [Limits of use](#) and [About Redis console](#) first.

Generally, you need to perform the following operations from instance buying to instance use.



Purpose of the document

This document describes how to create an ApsaraDB for Redis instance, helping you know the procedures from buying an ApsaraDB for Redis instance to using the instance.

Target reader

Users buying an ApsaraDB for Redis instance for the first time.

Users who want to know how to connect an ApsaraDB for Redis instance.

ApsaraDB for Redis console is a Web application that manages ApsaraDB for Redis instances. On the console, you can create and manage instances, set networks and passwords, and perform other operations on the user interface.

Prerequisites


You have logged on to ApsaraDB for Redis console by using your Alibaba Cloud account. If you do not have an Alibaba Cloud account, click [Register](#).

Console overview

Console homepage

The console homepage displays the same information for ApsaraDB for Redis instances of all types.

Log on to Redis Console, and go to the **Instance List** page, as shown in the following figure. (The figure here is just used for an example. Refer to the actual interface when using this document.)




On the **Instance List** page, the following information is displayed: **Instance ID**, **Status**, **Memory Quota and Amount Used**, **Zone**, **Creation Time**, **Billing Method**, and **Network Type**.

Note: **Memory Quota and Amount Used** is offline statistics made by the underlying system based on the collected information. A delay of about 10 minutes always exists.

Maintenance Window


You can modify the O&M period on the **Instance Information** page. Alibaba Cloud maintains the instances during the O&M time, which may result in system flash. It is recommended that you set the maintenance window in the idle service hours.



Performance Monitoring

Click **Instance ID** to go to the **Instance Information** page. In the left-side navigation bar, choose

Performance Monitoring to view historical performances of your ApsaraDB for Redis instances. Different metrics are displayed.



Different metrics are displayed after you click **Performance Monitoring**. Metrics of basic monitoring groups are described as follows.


Basic metrics	Description
Keys	Total number of keys of all backend ApsaraDB for Redis instances. Data on all backend nodes of a cluster instance is aggregated.
Expires	Total number of keys for which an expiration time is set.
ExpiredKeys	<p>Number of expired keys.</p> <p>The value is the sum of all expired keys, excluding the number of keys for which an expiration time is set but do not expire currently. Besides, it indicates the number of accumulated expired keys, instead of the number of expired keys in the current time.</p> <p>Note: In case of master-slave switchover, the value indicates the number of expired keys in the new master database.</p>
EvictedKeys	<p>Number of evicted keys.</p> <p>The value indicates the sum of keys which are evicted because the memory is used out, instead of the number of keys evicted in the current second.</p> <p>Note: In case of master-slave switchover, the value indicates the number of expired keys in the new master database.</p>
UsedMemory	<p>Memory in use currently.</p> <p>When a new instance is created, database metadata is generated. For master-slave instances, the generated database metadata occupies a space of at least 30 MB. For cluster instances, the generated database metadata</p>

	occupies a space of about 30 MB multiplied by the number of nodes. A space of at least 200 MB is occupied.
InFlow	Current traffic per second at the backend ApsaraDB for Redis ingress. The unit is KB/s.
OutFlow	Current traffic per second at the backend ApsaraDB for Redis egress. The unit is KB/s.
ConnCount	Count of current client connections of ApsaraDB for Redis.
FailedCount	<p>It makes no sense for master-slave instances because the client is directly connected to the backend database. For cluster instances, the parameter indicates the number of failed operations from Proxy to ApsaraDB for Redis, including the number of abnormal operations caused by timeout, disconnection or other exceptions.</p> <p>For some ApsaraDB for Redis of earlier versions, the value is a historical value. In such case, no error is reported when FaileCount is not set. For ApsaraDB for Redis of the new version, the value indicates the mean statistical value in each second. In the future, the value will indicate the mean statistical value in each second for ApsaraDB for Redis of later versions.</p>
TotalQps	QPS of ApsaraDB for Redis.
CpuUsage	CPU usage of the current ApsaraDB for Redis backend.

Note: You can click **Customize Metrics** to monitor the number of accesses to different operating commands, for example, the number of accesses to the set command per second. For details, refer to [Performance Monitoring](#).

Alarm Settings

Click **Alarm Settings** in the left-side navigation bar, and click the **Alarm Settings** button to go to the setting page of CloudMonitor.



You can create a metric for ApsaraDB for Redis instances as guided. It is recommended that you set a

memory metric for all cluster instances to monitor the memory of sub-nodes of the cluster instances.

System Parameters

You can set common parameters of ApsaraDB for Redis on the **System Parameters** page, for example, setting an eviction policy and notify-keyspace-events. For details, refer to **Parameter Settings**.

Backup and Restore

On the backup and recovery page, you can set a backup and the automatic backup time, and clone an instance. For details, refer to **Backup and Restore**.

Item	Description
List data type	The number of lists is not restricted. The size of single element shall not exceed 512 MB. It is recommended that one lists contain no more than 8192 elements, and the maximum value length shall not exceed 1 MB.
Set data type	The number of sets is not restricted. The size of single element shall not exceed 512 MB. It is recommended that one set contain no more than 8192 elements, and the maximum value length shall not exceed 1 MB.
SortedSet data type	The number of SortedSets is not restricted. The size of single element shall not exceed 512 MB. It is recommended that one SortedSet contain no more than 8192 elements, and the maximum value length shall not exceed 1 MB.
Hash data type	The number of fields is not restricted. The size of single element shall not exceed 512 MB. It is recommended that one field contain no more than 8192 elements, and the maximum value length shall not exceed 1 MB.
Restriction on the database number	Each instance supports 256 databases.
Redis commands supported	For details, refer to this document.
Monitoring alert	<p>ApsaraDB for Redis does not provide the capacity alert function. You can configure this function on CloudMonitor. For details, refer to this document.</p> <p>It is recommended that you set alert for the following metrics: instance fault, instance master-slave switchover, connection usage, failed operation count, capacity usage, write bandwidth usage, and read bandwidth usage.</p>

Expired data deletion policy	<ul style="list-style-type: none"> - Active expiration: The system periodically detects and deletes expired keys in the background. - Passive expiration: The system deletes expired keys when users access keys.
Idle connection recovery mechanism	Idle Redis connection is not automatically recovered by the server, and shall be managed by the user.
Data persistence policy	AOF_FSYNC_EVERYSEC is enabled , and fsync is performed every second.

ApsaraDB for Redis is compatible with Redis 3.0 and supports Redis 3.0 GEO commands. There are some commands temporarily unavailable and restricted commands.

Supported commands

Keys	String	Hash	List	Set	SortedSet
DEL	APPEND	HDEL	BLPOP	SADD	ZADD
DUMP	BITCOUNT	HEXISTS	BRPOP	SCARD	ZCARD
EXISTS	BITOP	HGET	BRPOPLPUSH	SDIFF	ZCOUNT
EXPIRE	BITPOS	HGETALL	LINDEX	SDIFFSTORE	ZINCRBY
EXPIREAT	DECR	HINCRBY	LINSERT	SINTER	ZRANGE
MOVE	DECRBY	HINCRBYFLOAT	LLEN	SINTERSTORE	ZRANGEBYSCORE
PERSIST	GET	HKEYS	LPOP	SISMEMBER	ZRANK
PEXPIRE	GETBIT	HLEN	LPUSH	SMEMBERS	ZREM
PEXPTREAT	GETRANGE	HMGET	LPUSHX	SMOVE	ZREMRANGEBYRANK
PTTL	GETSET	HMSET	LRANGE	SPOP	ZREMRANGEBYSCORE
RANDOMKEY	INCR	HSET	LREM	SRANDMEMBER	ZREVRANGE
RENAME	INCRBY	HSETNX	LSET	SREM	ZREVRANGEBYSCORE
RENAMENX	INCRBYFLOAT	HVALS	LTRIM	SUNION	ZREVRANK
RESTORE	MGET	HSCAN	RPOP	SUNIONSTORE	ZSCORE
SORT	MSET		RPOPLPUSH	SSCAN	ZUNIONSTORE

TTL	MSETNX		RPUSH		ZINTERSTORE
TYPE	PSETEX		RPUSHX		ZSCAN
SCAN	SET				ZRANGEBYLEX
OBJECT	SETBIT				ZLEXCOUNT
	SETEX				ZREMRANGEBYLEX
	SETNX				
	SETRANGE				
	STRLEN				

And

HyperLog Log	Pub/Sub (publish/subscription)	Transaction	Connection	Server	Scripting	Geo (geographical position)
PFADD	PSUBSCRIBE	DISCARD	AUTH	FLUSHALL	EVAL	GEOADD
PFCOUNT	PUBLISH	EXEC	ECHO	FLUSHDB	EVALSHA	GEOHASH
PFMERGE	PUBSUB	MULTI	PING	DBSIZE	SCRIPT EXISTS	GEOPOS
	PUNSUBSCRIBE	UNWATCH	QUIT	TIME	SCRIPT FLUSH	GEODIST
	SUBSCRIBE	WATCH	SELECT	INFO	SCRIPT KILL	GEORADIUS
	UNSUBSCRIBE			KEYS	SCRIPT LOAD	GEORADIUSBYMEMBER
				CLIENT KILL		
				CLIENT LIST		
				CLIENT GETNAME		
				CLIENT SETNAME		
				CONFIG GET		
				MONITOR		

				R		
				SLOWLOG		

Commands temporarily unavailable

Keys	Server
MIGRATE	BGREWRITEAOF
	BGSAVE
	CONFIG REWRITE
	CONFIG SET
	CONFIG RESETSTAT
	COMMAND
	COMMAND COUNT
	COMMAND GETKEYS
	COMMAND INFO
	DEBUG OBJECT
	DEBUG SEGFAULT
	LASTSAVE
	ROLE
	SAVE
	SHUTDOWN
	SLAVEOF
	SYNC

Commands not supported by cluster instances

Scripting	Keys	Server
EVAL	SCAN	CLIENT KILL
EVALSHA		CLIENT LIST
SCRIPT EXISTS		CLIENT GETNAME
SCRIPT FLUSH		CLIENT SETNAME
SCRIPT KILL		MONITOR
SCRIPT LOAD		

Commands restricted for cluster instances

Keys	Strings	Lists	Sets	Sorted Sets	HyperLog Log	Transaction
RENAME	MSETNX	RPOPLPUSH	SINTERSTORE	ZUNIONSTORE	PFMERGE	DISCARD
RENAME NX			SINTER	ZINTERSTORE	PFCOUNT	EXEC
SORT			SUNIONSTORE			MULTI
			SUNION			UNWATCH
			SDIFFSTORE			WATCH
			SDIFF			
			SMOVE			

Note:

Restricted commands support only scenarios where keys to be operated are evenly distributed in a single hash slot and cannot merge hash slot data. Therefore, you need to use the hash tag to ensure keys to be operated are evenly distributed in one hash slot.

For example, if there are key1, aa{key}, and ab{key}3 to be operated, you need to store them in the {key}1, aa{key}, and ab{key}3 mode, so that restricted commands can take effect when being called. For detailed usage of hash tag, refer to the official document of ApsaraDB for Redis at: <http://redis.io/topics/cluster-spec>.

For details about Redis commands, refer to this [official document](#).

ApsaraDB for Redis supports Pay-As-You-Go instances. The following describes how to buy a Pay-As-You-Go instance.

Prerequisites

Before activating ApsaraDB for Redis, you need to have at least one ECS instance. For details about how to buy an ECS instance, refer to [Buy an ECS instance](#).

Procedure

Go to ApsaraDB for Redis homepage, and click **Buy Now**. Or you can log on to Redis Console and click **Create Instance** in the upper-right corner.

Choose **Region**, **Zone**, **Instance Type**, **Network Type**, and **Quantity**, and set the **Logon Password** and **Instance Name**.

Note:

Through configuration change, a master-slave instance can become a cluster instance which has functions different to those of the master-slave instance. For details, refer to **Commands supported by ApsaraDB for Redis**.

ApsaraDB for Redis can be accessed only through the intranet. It is recommended that you configure ApsaraDB for Redis instance and the ECS instance in the same zone of the same region.

Click **Buy Now** to go to the **Confirm Order** page. Read and accept the Terms of Service for ApsaraDB for Redis, check the order information, and click **Pay Now** to make the payment.

Select a payment method on the payment page and click the **Confirm** button. After the payment is made, a message that reads "Payment Successful" will be displayed. After one to five minutes you can log on to the console to view the instance bought.

Note: ApsaraDB for Redis is consistent with Redis in terms of product behavior. When a new instance is created, it generates database metadata which occupies a fraction of the instance's storage space. The occupied space is shown on the ApsaraDB for Redis Console.

For master-slave instances, the generated database metadata occupies a space of about 32 MB.

For cluster instances, the generated database metadata occupies a space of about 32 MB multiplied by the number of nodes.

Connect to Redis

As ApsaraDB for Redis is completely compatible with the native database service, their databases are connected in similar ways. Any clients compatible with the Redis protocol can access Alibaba Cloud ApsaraDB for Redis. You can choose any Redis clients based on their application features.

Note: ApsaraDB for Redis only supports access requests from the Alibaba Cloud intranet rather than those from the Internet. That means only Redis clients installed on ECS instances of the same node can be connected to ApsaraDB for Redis for data operations.

To use Redis clients, refer to this [official document](#).

- Jedis client
- phpredis client
- redis-py client
- C/C++ client
- .net client
- node-redis client

Jedis client

The Jedis client can access ApsaraDB for Redis through either of the following methods:

Jedis single-connection

JedisPool connection

Procedure

Click [download address](#) to download and install the Jedis client.

Example of Jedis single-connection

Open the Eclipse client, create a project, and enter the following code segment:

```
import redis.clients.jedis.Jedis;

public class jedistest {
    public static void main(String[] args) {
        try {
            String host = "xx.kvstore.aliyuncs.com";//The access URL is displayed on the console.
            int port = 6379;
            Jedis jedis = new Jedis(host, port);
            //Authentication information
            jedis.auth("password");//password
```

```
String key = "redis";
String value = "aliyun-redis";
//Select a database. (The default value is 0.)
jedis.select(1);
//Set a key.
jedis.set(key, value);
System.out.println("Set Key " + key + " Value: " + value);
//Get the key.
String getvalue = jedis.get(key);
System.out.println("Get Key " + key + " ReturnValue: " + getvalue);
jedis.quit();
jedis.close();
} catch (Exception e) {
    e.printStackTrace();
}
}
```

Run the project. If the following result is output on the Eclipse console, you have successfully connected to ApsaraDB for Redis.

```
Set Key redis Value aliyun-redis
Get Key redis ReturnValue aliyun-redis
```

Then you can use your local Jedis client to operate your ApsaraDB for Redis instance. You can also connect to your ApsaraDB for Redis instance through JedisPool.

Example of JedisPool connection

Open the Eclipse client, create a project, and configure the pom file as follows:

```
<dependency>
<groupId>redis.clients</groupId>
<artifactId>jedis</artifactId>
<version>2.7.2</version>
<type>jar</type>
<scope>compile</scope>
</dependency>
```

Add the following application to the project:

```
import org.apache.commons.pool2.PooledObject;
import org.apache.commons.pool2.PooledObjectFactory;
import org.apache.commons.pool2.impl.DefaultPooledObject;
import org.apache.commons.pool2.impl.GenericObjectPoolConfig;

import redis.clients.jedis.HostAndPort;
```

```
import redis.clients.jedis.Jedis;
import redis.clients.jedis.JedisPool;
import redis.clients.jedis.JedisPoolConfig;
```

If your Jedis client version is Jedis-2.7.2, enter the following code in the project:

```
JedisPoolConfig config = new JedisPoolConfig();
//Maximum idle connections, which are evaluated by the application. Do not set it to a value
greater than the maximum connections of an ApsaraDB for Redis instance.
config.setMaxIdle(200);
//Maximum connections, which are evaluated by the application. Do not set it to a value
greater than the maximum connections of an ApsaraDB for Redis instance.
config.setMaxTotal(300);
config.setTestOnBorrow(false);
config.setTestOnReturn(false);

String host = "*.aliyuncs.com";
String password = "password";
JedisPool pool = new JedisPool(config, host, 6379, 3000, password);
Jedis jedis = null;
try {
jedis = pool.getResource();
/// ... do stuff here ... for example
jedis.set("foo", "bar");
String foobar = jedis.get("foo");
jedis.zadd("sose", 0, "car");
jedis.zadd("sose", 0, "bike");
Set<String> sose = jedis.zrange("sose", 0, -1);
} finally {
if (jedis != null) {
jedis.close();
}
}
/// ... when closing your application:
pool.destroy();
```

If your Jedis client version is Jedis-2.6 or Jedis-2.5, enter the following code in the project:

```
JedisPoolConfig config = new JedisPoolConfig();
//Maximum idle connections, which are evaluated by the application. Do not set it to a value
greater than the maximum connections of an ApsaraDB for Redis instance.
config.setMaxIdle(200);
//Maximum connections, which are evaluated by the application. Do not set it to a value
greater than the maximum connections of an ApsaraDB for Redis instance.
config.setMaxTotal(300);
config.setTestOnBorrow(false);
config.setTestOnReturn(false);
String host = "*.aliyuncs.com";
String password = "password";
JedisPool pool = new JedisPool(config, host, 6379, 3000, password);
Jedis jedis = null;
```

```
boolean broken = false;
try {
    jedis = pool.getResource();
    /// ... do stuff here ... for example
    jedis.set("foo", "bar");
    String foobar = jedis.get("foo");
    jedis.zadd("sose", 0, "car");
    jedis.zadd("sose", 0, "bike");
    Set<String> sose = jedis.zrange("sose", 0, -1);
} catch (Exception e) {
    broken = true;
} finally {
    if (broken) {
        pool.returnBrokenResource(jedis);
    } else if (jedis != null) {
        pool.returnResource(jedis);
    }
}
```

Run the project. If the following result is output on the Eclipse console, you have successfully connected to ApsaraDB for Redis.

```
Set Key redis Value aliyun-redis
Get Key redis ReturnValue aliyun-redis
```

Then you can use your local Jedis client to operate your ApsaraDB for Redis instance.

phpredis client

Procedure

Click [download address](#) to download and install the phpredis client.

In any editor supporting php editing, enter the following code:

```
<?php
/* Replace the following parameter values with the host of the connected instance and the port number. */
$host = "localhost";
$port = 6379;

/* Replace the following parameter values with the instance ID and instance password. */
$user = "test_username";
$pwd = "test_password";
$redis = new Redis();
if ($redis->connect($host, $port) == false) {
    die($redis->getLastError());
}
```

```
if ($redis->auth($pwd) == false) {  
    die($redis->getLastError());  
}  
/* The database can be operated after authentication. For details, refer to  
https://github.com/phpredis/phpredis. */  
if ($redis->set("foo", "bar") == false) {  
    die($redis->getLastError());  
}  
$value = $redis->get("foo");  
echo $value;  
?>
```

3. Run the preceding code. Then You can use your local phpredis client to access your ApsaraDB for Redis instance. For details, refer to <https://github.com/phpredis/phpredis>.

redis-py client

Procedure

Click download address to download and install the redis-py client.

In any editor supporting Python editing, enter the following code. Then you can use a local redis-py client to connect to and operate the database.

```
#!/usr/bin/env python  
#-*- coding: utf-8 -*-  
import redis  
  
#Replace the following parameter values with the host of the connected instance and the port number.  
host = 'localhost'  
port = 6379  
  
#Replace the following parameter values with the instance password.  
pwd = 'test_password'  
r = redis.StrictRedis(host=host, port=port, password=pwd)  
  
#The database can be operated after a connection is created. For details, refer to  
https://github.com/andymccurdy/redis-py.  
r.set('foo', 'bar');  
print r.get('foo')
```

C/C++ client

Procedure

Download, compile, and install the C client. The code for compiling and installation is as follows:

```
git clone https://github.com/redis/hiredis.git
cd hiredis
make
sudo make install
```

Enter the following code in the C/C++ editor:

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <hiredis.h>
int main(int argc, char **argv) {
    unsigned int j;
    redisContext *c;
    redisReply *reply;
    if (argc < 4) {
        printf("Usage: example xxx.kvstore.aliyuncs.com 6379 instance_id password\n");
        exit(0);
    }
    const char *hostname = argv[1];
    const int port = atoi(argv[2]);
    const char *instance_id = argv[3];
    const char *password = argv[4];
    struct timeval timeout = { 1, 500000 }; // 1.5 seconds
    c = redisConnectWithTimeout(hostname, port, timeout);
    if (c == NULL || c->err) {
        if (c) {
            printf("Connection error: %s\n", c->errstr);
            redisFree(c);
        } else {
            printf("Connection error: can't allocate redis context\n");
        }
        exit(1);
    }
    /* AUTH */
    reply = redisCommand(c, "AUTH %s", password);
    printf("AUTH: %s\n", reply->str);
    freeReplyObject(reply);
    /* PING server */
    reply = redisCommand(c, "PING");
    printf("PING: %s\n", reply->str);
    freeReplyObject(reply);
    /* Set a key */
    reply = redisCommand(c, "SET %s %s", "foo", "hello world");
    printf("SET: %s\n", reply->str);
    freeReplyObject(reply);
    /* Set a key using binary safe API */
    reply = redisCommand(c, "SET %b %b", "bar", (size_t) 3, "hello", (size_t) 5);
    printf("SET (binary API): %s\n", reply->str);
    freeReplyObject(reply);
}
```

```

/* Try a GET and two INCR */
reply = redisCommand(c,"GET foo");
printf("GET foo: %s\n", reply->str);
freeReplyObject(reply);
reply = redisCommand(c,"INCR counter");
printf("INCR counter: %lld\n", reply->integer);
freeReplyObject(reply);
/* again ... */
reply = redisCommand(c,"INCR counter");
printf("INCR counter: %lld\n", reply->integer);
freeReplyObject(reply);
/* Create a list of numbers, from 0 to 9 */
reply = redisCommand(c,"DEL mylist");
freeReplyObject(reply);
for (j = 0; j < 10; j++) {
    char buf[64];
    snprintf(buf,64,"%d",j);
    reply = redisCommand(c,"LPUSH mylist element-%s", buf);
    freeReplyObject(reply);
}
/* Let's check what we have inside the list */
reply = redisCommand(c,"LRANGE mylist 0 -1");
if (reply->type == REDIS_REPLY_ARRAY) {
    for (j = 0; j < reply->elements; j++) {
        printf("%u) %s\n", j, reply->element[j]->str);
    }
}
freeReplyObject(reply);
/* Disconnects and frees the context */
redisFree(c);
return 0;
}

```

Compile the preceding code.

```
gcc -o example -g example.c -I /usr/local/include/hiredis -lhiredis
```

Perform the test run.

```
example xxx.kvstore.aliyuncs.com 6379 instance_id password
```

So far, the C/C++ client can connect to ApsaraDB for Redis.

.net client

Procedure

Download and use the .net client.

```
git clone https://github.com/ServiceStack/ServiceStack.Redis
```

Create a .net project in the .net client.

Add the reference file stored in the library file directory ServiceStack.Redis/lib/tests to the client.

Enter the following code in the created .net project to connect to ApsaraDB for Redis. For details about port use, refer to <https://github.com/ServiceStack/ServiceStack.Redis>.

```
using System;
using System.Collections.Generic;
using System.Linq;
using System.Text;
using System.Threading.Tasks;
using ServiceStack.Redis;
namespace ServiceStack.Redis.Tests
{
    class Program
    {
        public static void RedisClientTest()
        {
            string host = "127.0.0.1"; /*IP address of the access host*/
            string password = "password"; /*Password*/
            RedisClient redisClient = new RedisClient(host, 6379, password);
            string key = "test-aliyun";
            string value = "test-aliyun-value";
            redisClient.Set(key, value);
            string listKey = "test-aliyun-list";
            System.Console.WriteLine("set key " + key + " value " + value);
            string getValue = System.Text.Encoding.Default.GetString(redisClient.Get(key));
            System.Console.WriteLine("get key " + key + " value " + getValue);
            System.Console.Read();
        }
        public static void RedisPoolClientTest()
        {
            string[] testReadWriteHosts = new[] {
                "redis://password@127.0.0.1:6379" /*redis://password@access address:port number*/
            };
            RedisConfig.VerifyMasterConnections = false; /*You need to set the parameter.*/
            PooledRedisClientManager redisPoolManager = new PooledRedisClientManager(10 /*Number of connection pools*/, 10 /*Connection pool timeout time*/, testReadWriteHosts);
            for (int i = 0; i < 100; i++) {
                IRedisClient redisClient = redisPoolManager.GetClient(); /*Obtain the connection.*/
                RedisNativeClient redisNativeClient = (RedisNativeClient)redisClient;
                redisNativeClient.Client = null; /*ApsaraDB for Redis does not support client setname. Therefore, you need to set the client object to null.*/
                try
                {
                    string key = "test-aliyun1111";
                    string value = "test-aliyun-value1111";
```

```
redisClient.Set(key, value);
string listKey = "test-aliyun-list";
redisClient.AddItemToList(listKey, value);
System.Console.WriteLine("set key " + key + " value " + value);
string getValue = redisClient.GetValue(key);
System.Console.WriteLine("get key " + getValue);
redisClient.Dispose();//
}catch (Exception e)
{
    System.Console.WriteLine(e.Message);
}
}
System.Console.Read();
}static void Main(string[] args)
{
    //Single connection mode
    RedisClientTest();
    //Connection pool mode
    RedisPoolClientTest();
}
}
}
```

node-redis client

Procedure

Download and install node-redis.

```
npm install hiredis redis
```

Enter and run the following code in the node-redis client to connect to ApsaraDB for Redis.

```
var redis = require("redis"),
client = redis.createClient({detect_buffers: true});
client.auth("password", redis.print)
```

Use ApsaraDB for Redis.

```
// Write data.
client.set("key", "OK");
// Obtain data and a string is returned.
client.get("key", function (err, reply) {
    console.log(reply.toString()); // print `OK`
});
// If a buffer is transmitted, a buffer will be returned.
client.get(new Buffer("key"), function (err, reply) {
```

```
console.log(reply.toString()); // print `<Buffer 4f 4b>`  
});  
client.quit();
```

ApsaraDB for Redis only supports access from Alibaba Cloud intranet. It does not support Internet accesses. That is, only clients of ApsaraDB for Redis installed on ECSs of the same node can be connected to ApsaraDB for Redis for data operations.

Note: Redis-cli is the native command line interface for Redis. You can first download and install Redis on ECS before using Redis-cli. For the Redis installation commands, refer to the official document [here](#).

You can run the following redis-cli command to connect to ApsaraDB for Redis:

```
redis-cli -h instance connection address -a Password
```

ECS Windows

Currently, ApsaraDB for Redis is accessible through ECS intranet. If you need to locally access ApsaraDB for Redis through Internet, you can create a port mapping through netsh on the ECS Windows server.

Log on to ECS Windows server and run the following command in the CMD window:

```
netsh interface portproxy add v4tov4 listenaddress=public IP address of ECS listenport=6379  
connectaddress=connection address of ApsaraDB for Redis connectport=6379
```

In the preceding command:

netsh interface portproxy delete v4tov4 listenaddress=public IP address of ECS
listenport=6379 can be used to delete unnecessary mappings.

netsh interface portproxy show all can be used to show mappings on the current
server.

Perform a verification test after configuration is completed.

Run the redis-cli command locally to connect to the ECS Windows server and perform read and write operations. For example, if the IP address of the ECS Windows server is 1.1.1.1,

you can telnet to 1.1.1.1 6379.

After performing the preceding steps, you can use a local PC or server to connect to Port 6379 of ECS Windows server to access ApsaraDB for Redis through a public network.

Note: As portproxy is provided by Microsoft rather than open source, refer to the netsh documentation on portproxy or consult Microsoft engineers for any questions during the configuration process. Or you can use alternative scheme to do the same. For example, use portmap to configure proxy mappings.

ECS Linux

Currently, ApsaraDB for Redis is accessible through ECS intranet. If you need to locally access ApsaraDB for Redis through a public network, you can install rinetd on the ECS Linux server.

Install rinetd on the ECS Linux server.

```
wget http://www.boutell.com/rinetd/http/rinetd.tar.gz&&tar -xvf rinetd.tar.gz&&cd rinetd
sed -i 's/65536/65535/g' rinetd.c (Modify the port range)
mkdir /usr/man&&make&&make install
```

Note: The rinetd installation package obtained from the download URL may be unavailable. You can find and download the rinetd installation package from other sources.

Create the configuration file.

```
vi /etc/rinetd.conf
```

Enter the following information:

```
0.0.0.0 6379 Connection address of Port 6379 of ApsaraDB for Redis
logfile /var/log/rinetd.log
```

Run the following command to start rinetd.

```
rinetd
```

Note:

You can use `echo rinetd >>/etc/rc.local` to enable rinetd to start automatically.

You can run `kill rinetd` to stop the `rinetd` process.

Perform a verification test.

Run `redis-cli` locally to connect to the ECS Linux server for logon authentication. For example, if the IP address of the server with `rinetd` installed is `1.1.1.1`, you can run the following command:

```
redis-cli -h 1.1.1.1 -a Instance ID of ApsaraDB for Redis: Password of ApsaraDB for Redis
```

After performing the preceding steps, you can use a local PC or server to connect to Port 6379 of ECS Linux server to access ApsaraDB for Redis through a public network.

Note: You can use the above scheme to test and use `rinetd`. Since `rinetd` is open source software, if you have any problems in use, read its official documentation or contact `rinetd` engineers for help.